



Maintenance Message Banner

Product specification

Maintenance Message Banner is a Magento 2 extension developed by PIT solutions which enables admin users to inform customers about the maintenance timing or down time earlier via a banner on top of every page.

Features

- Enables admin users to show customized maintenance notification message in the frontend.
- Message can be shown all the time until it is disabled or can be scheduled to display/hide automatically within a time interval.
- Supports access control for admin users.

Prerequisites

Magento Community 2.3.x, 2.4.x

Installation

To install Maintenance Message Banner module, follow the steps below.

Step 1: Download Maintenance Message module extension and unzip it.

Step 2: Access your web server directories and upload the content of the folder into `app/code/Pits/MaintenanceMessage/` directory.


Step 3: Run the following commands to complete the installation.

1. Enable the module - `php bin/magento module:enable`
2. Update of the database - `php bin/magento setup:upgrade`
3. Generate and pre-compile classes - `php bin/magento setup:di:compile`
4. Deploy static files - `php bin/magento setup:static-content:deploy`




Screenshots / Video

From the admin backend, go to **Stores > PITS Configuration > Maintenance Manager**



Configure Message Manager

- Enable the module.
 1. Select **Yes** to display the message all the time.





2. Select **Time Interval** to display the message within the time interval and automatically hide it after the interval.

Configuration

Store View: Default Config

Save Config

GENERAL

PITS CONFIGURATION

Maintenance Manager

CATALOG

SECURITY

CUSTOMERS

SALES

ENGAGEMENT CLOUD

SERVICES

ADVANCED

General Settings

Enable [store view] Time Interval

Enable maintenance message to display in shop frontend

Start Time [store view] 27-05-2020 14:00

Maintenance message is displayed at this hour.

End Time [store view] 27-05-2020 16:00

Maintenance message is disabled at this hour.

Message [store view] Maintenance: The shop will be down for maintenance on Wednesday May 27 from 16:00 to 18:00 UTC. Sorry for the inconvenience.

Enter Maintenance message

Copyright © 2020 Magento Commerce Inc. All rights reserved.

Magento ver. 2.3.2
[Report an Issue](#)

- Enter **Start Time** (available only if Time Interval option is selected).
- Enter **End Time** (available only if Time Interval option is selected).
- Enter the **Message**.
- Click **Save Config** and clear the cache.

The message will be displayed in the frontend as below.

Maintenance: The shop will be down for maintenance on Wednesday May 27 from 16:00 to 18:00 UTC. Sorry for the inconvenience.

Default welcome msg! Sign In or Create an Account

LUMA

Home Page

CMS homepage content goes here.

Search Terms
Privacy and Cookie Policy
Orders and Returns
Contact Us
Advanced Search

Enter your email address

Subscribe

Copyright © 2013 present Magento, Inc. All rights reserved.

Manage User Role

Step 1 : Go to Admin > System > User Roles



The screenshot shows the Magento 2 System menu. The 'User Roles' option is highlighted with a red box. The menu includes sections for Data Transfer, Import, Export, Import/Export Tax Rates, Import History, Extensions, Integrations, Tools, Cache Management, Backups, Index Management, and Web Setup Wizard. The 'User Roles' option is located under the 'Permissions' section.

Step 2 : Add a new role resource

Fill in the role information section.

New Role

The screenshot shows the 'New Role' form in Magento 2. The form is divided into two main sections: 'Role Information' and 'Current User Identity Verification'. The 'Role Information' section contains a 'Role Name' field with the value 'admin'. The 'Current User Identity Verification' section contains a 'Your Password' field with masked characters (dots).

ROLE INFORMATION

Role Info

Role Name * admin














Role Resources

Current User Identity Verification

Your Password *

Select **Maintenance Message** role at Role Resources section.



- ▶  Payment Services
- ▶  Shipping Methods Section
- ▶  Shipping Policy Parameters Section
- ▶  Shipping Settings Section
- ▶  Multishipping Settings Section
- ▶  General Section
- ▶  Maintenance Message
- ▶  Web Section
- ▶  Design Section
- ▶  Security Suite
 - ▶  ReCaptcha
 - ▶  Two Factor Auth
- ▶  Customers Section

Step 3: Set role users for admin accounts, then click on **Save Role** to finish.

Supported Languages

English and other Magento supported language packs.

Change Log / Release Notes

Version: 1.0.6: September 21, 2023

- Updated translation

Version: 1.0.5: March 22, 2023

- Compatible with Open Source (CE) : 2.4.6

Version: 1.0.4: October 5, 2022

- Compatible with Open Source (CE) : 2.4.5

Version: 1.0.3: June 27, 2022

- Compatible with Open Source (CE) : 2.4.4

Version: 1.0.2: January 11, 2022

- Updated copyright information

Version: 1.0.1: January 19, 2021

- Compatible with Open Source (CE) : 2.4.x.



Version: 1.0.0: May 29, 2020

- Admin configuration to show customized maintenance notification message in the frontend.
- Added scheduled message display option.
- Added access control for admin users.

Support

If you have questions use our contact form in webshopextension.com.