



Maintenance Message Banner

Prerequisites

Magento Community 2.1.x, 2.2.x, 2.3.x, 2.4.x

Installation

To install Maintenance Message Banner module follow the steps below.

Step 1: Download Maintenance Message module extension and unzip it.

Step 2: Access your web server directories and upload the content of the folder into app/code/Pits/MaintenanceMessage/ directory.

Step 3: Run the following commands to complete the installation.

1. Enable the module - `php bin/magento module:enable`
2. Update of the database - `php bin/magento setup:upgrade`
3. Generate and pre-compile classes - `php bin/magento setup:di:compile`
4. Deploy static files - `php bin/magento setup:static-content:deploy`

Configuration

From the admin backend, go to **Stores > PITS Configuration > Maintenance Manager**

The screenshot shows the Magento admin interface. On the left, a sidebar menu is open to the 'Stores' section, with 'Configuration' highlighted. The main content area displays the 'Maintenance Manager' configuration page. A 'Save Config' button is visible at the top right. Below the button, there is a dropdown menu for selecting a 'Maintenance message to display in shop frontend'. A preview of the selected message is shown below the dropdown, displaying: 'The shop will be down for maintenance on May 27 from 16:00 to 18:00 UTC. Sorry for the inconvenience.' At the bottom of the page, the footer contains the text 'Copyright © 2020 Magento Commerce Inc. All rights reserved.' and 'Magento ver. 2.3.2 Report an issue'.



Configure Message Manager

- Enable the module.
 1. Select **Yes** to display the message all the time.

The screenshot shows the Magento Configuration interface. On the left sidebar, the 'PITS CONFIGURATION' menu is expanded, and 'Maintenance Manager' is selected. The main content area is titled 'General Settings'. The 'Enable' dropdown is set to 'Yes', with the description 'Enable maintenance message to display in shop frontend'. The 'Message' text area contains the text: 'Maintenance: The shop will be down for maintenance on Wednesday May 27 from 16:00 to 18:00 UTC. Sorry for the inconvenience.' Below the text area is a label 'Enter Maintenance message'. The footer shows 'Copyright © 2020 Magento Commerce Inc. All rights reserved.' and 'Magento ver. 2.3.2 Report an Issue'.

2. Select **Time Interval** to display the message within the time interval and automatically hide it after the interval.


The screenshot shows the Magento Configuration interface. On the left sidebar, the 'PITS CONFIGURATION' menu is expanded, and 'Maintenance Manager' is selected. The main content area is titled 'General Settings'. The 'Enable' dropdown is set to 'Time Interval', with the description 'Enable maintenance message to display in shop frontend'. The 'Start Time' is set to '27-05-2020 14:00' with the description 'Maintenance message is displayed at this hour.' The 'End Time' is set to '27-05-2020 16:00' with the description 'Maintenance message is disabled at this hour.' The 'Message' text area contains the text: 'Maintenance: The shop will be down for maintenance on Wednesday May 27 from 16:00 to 18:00 UTC. Sorry for the inconvenience.' Below the text area is a label 'Enter Maintenance message'. The footer shows 'Copyright © 2020 Magento Commerce Inc. All rights reserved.' and 'Magento ver. 2.3.2 Report an Issue'.

- Enter **Start Time** (available only if Time Interval option is selected).




- Enter **End Time** (available only if Time Interval option is selected).
- Enter the **Message**.
- Click **Save Config** and clear the cache.

The message will be displayed in the frontend as below.



Manage User Role

Step 1 : Go to Admin > System > User Roles



Step 2 : Add a new role resource



Fill in the role information section.

New Role

ROLE INFORMATION

Role Info

Role Resources

Role Information

Role Name *

Current User Identity Verification

Your Password *

Select **Maintenance Message** role at Role Resources section.

- ▶ Payment Services
- ▶ Shipping Methods Section
- ▶ Shipping Policy Parameters Section
- ▶ Shipping Settings Section
- ▶ Multishipping Settings Section
- ▶ General Section
- ▶ Maintenance Message
- ▶ Web Section
- ▶ Design Section
- ▶ Security Suite
 - ▶ ReCaptcha
 - ▶ Two Factor Auth
- ▶ Customers Section

Step 3: Set role users for admin accounts, then click on **Save Role** to finish.

Support

If you have questions use our contact form in webshopextension.com.